



SymbianGuru.com Your guru in mobile software.

www.symbianguru.com


support@symbianguru.com

PhotoFun v 1.2



by SymbianGuru

User Manual




SymbianGuru.com Your guru in mobile software.

www.symbianguru.com

support@symbianguru.com

Index

General description	3
How to register PhotoFun	4
How to install PhotoFun.....	4
Working with PhotoFun.....	4
How to start	4
General information	4
First application start.....	4
PhotoFun Options	5
<i>Change template</i>	6
<i>Night mode /Flash mode</i>	6
<i>Settings</i>	6
Camera orientation troubleshooting.....	7
New templates creating.....	8
Templates in MS Paint	8
Templates in Adobe PhotoShop	9
Sharing Templates.....	9
How to uninstall PhotoFun v 1.2	9
PhotoFun Support	9



SymbianGuru.com Your guru in mobile software.

www.symbianguru.com


support@symbianguru.com

General description

PhotoFun Software allows making funny photos merging the predefined templates with phone camera. Some templates are shipped with the application; more templates can be downloaded from the vendor's site or made from your own photos.

Version 1.2 PhotoFun is compatible with **Series 60.3, 60.5 and S^3 Symbian** smartphones:

Nokia 3250	Nokia N92
Nokia 5500	Nokia N93
Nokia 5700	Nokia N93i
Nokia 6120	Nokia N95
Nokia 6121	Nokia C5-03
Nokia 6110 Navigator	Nokia 5250
Nokia E50	Nokia 5228
Nokia E51	Nokia C6-00
Nokia E61i	Nokia 5230 Nuron
Nokia E62	Nokia 5235 Ovi Music Unlimited
Nokia E65	Nokia N97 mini
Nokia E70	Nokia X6-00
Nokia E90	Nokia 5230
Nokia N71	Nokia 5530 XpressMusic
Nokia N73	Nokia N97
Nokia N73 Music Edition	Nokia 5800 XpressMusic
Nokia N75	Nokia C6-01
Nokia N76	Nokia C7-00
Nokia N77	Nokia E7-00
Nokia N80	Nokia N8-00
Nokia N81	Samsung SGH-i520
Nokia N91	LG JoY
Nokia N91 8GB	



SymbianGuru.com Your guru in mobile software.

www.symbianguru.com

support@symbianguru.com

How to register PhotoFun

The trial version of the software is limited to 10 days. During 10 days you can test the application with full features. After 10 days you will not be able to launch the application unless registered.

The full version of the software is obtained by a license code provided upon purchase. The license code is based on the unique IMEI provided and the application can be used exclusively on the device it is licensed for. The license cannot be retrieved and applied to other devices.

How to install PhotoFun

Please transfer the .SIS file to your mobile phone via Bluetooth, IRDA or Cable. Then follow the installation instructions on the mobile screen. You may install this software either on your phone memory or your MMC.

Working with PhotoFun

How to start

PhotoFun Application can be opened in following ways (depending on the phone):


- Clicking on the Menu button → PhotoFun
- Clicking on the Menu button → My Own/Applications → PhotoFun

General information

PhotoFun application gives you possibility to make photo with different funny templates, which you have previously selected. The software has some templates preinstalled, but you also can make your own templates or download more templates from SymbianGuru page www.symbianguru.com .

First application start

After launching the application you are able to make photos with the default template immediately by pressing Joystick OK key.



SymbianGuru.com Your guru in mobile software.

www.symbianguru.com


support@symbianguru.com




PhotoFun Options

When you press the left soft key Options you have the following possibilities:

- Change template – allows to change the templates
- Night mode – allows to activate or deactivate the night mode
- Flash mode – allows to activate/deactivate the Flash mode or make this mode automatic
- Settings – settings of the software, which you can change
- Register – field for entering Registration Code
- Buy – allows buying the PhotoFun application online
- Help – short info for user to use the software
- About – short info about company and contacts
- Exit – exit the application





SymbianGuru.com Your guru in mobile software.

www.symbianguru.com

support@symbianguru.com

Change template

To change the current template you have to click left soft key Options → Change template. You will have to select one from the list of all possible templates by pressing Joystick OK key or pressing Select item from Options menu.



Also you are able to select such options from Options menu

- Select – select current template
- Preview – preview current template
- Delete – delete current template
- Delete all – delete all templates

Night mode /Flash mode


You can activate or deactivate the night mode by pressing Options →Night mode→ On/Off

To activate/deactivate the Flash mode or make this mode automatic you should press left soft key Options → Flash mode → On/Off/Automatic.

Note: some mobile phones have no flash, so this option will be unavailable.

Settings


By pressing left soft key Options→ Settings you will be able to change the following:



SymbianGuru.com Your guru in mobile software.

www.symbianguru.com


support@symbianguru.com




1. Image quality (High/Normal/Basic) – This depends on what photo you want to receive and where this photo will be using. If you want to receive a super photo image you should select the high quality option. If not you can select the normal or basic. The optimal option is Basic.
2. Show captured image (On/Off) – if you want to see the captured image, this option should be turned on
3. Default image name (Date/Text) – this option help you to define the name of the photo; it can be saved by date or by the default name, which can be edited (the default name is ‚FunnyImage’).
4. Memory in use (Phone memory/Memory card) – you should select the memory, where your photos will be saved
5. Image resolution – here you can select the resolution of your photos. Higher resolution means more image detail.

Camera orientation troubleshooting

If you see query dialog "Proceed with such camera orientation?" on first application start and camera orientation is incorrect you can refuse it by pressing soft-key No. If such orientation is acceptable for you in this case you should press soft-key Yes.





SymbianGuru.com Your guru in mobile software.

www.symbianguru.com

support@symbianguru.com

If you choose wrong orientation by mistake you can change camera orientation by using Orientation option (Options → Settings → Orientation). This option allows you to select camera orientation from portrait and landscape modes.




New templates creating

To create your own template you have the picture of which you want to create the template. You can create your own template with the help of MS Paint or Adobe Photoshop, or any other graphical redactor that you like.

Templates in MS Paint

If you want to create your own template with the help of MS Paint you will have to do the following:

1. Launch paint application on your PC and insert your image. Note: The image size should be 320(w)*240(h) to fit your mobile screen
2. Fill the region which should be transparent with the contrast colour that is not present on your picture.
3. Fill with the same colour the upper left pixel.
4. Save your picture in *.PNG format. The file extension should be changed from capital letters to the small letters (e.g. name.png, not name.PNG)
5. Upload image to your phone with the help of Bluetooth or data cable to the PhotoFun - Templates folder on Phone memory or Data - Photofun - Templates folder.



SymbianGuru.com Your guru in mobile software.

www.symbianguru.com

support@symbianguru.com

Templates in Adobe PhotoShop

If you are going to create your own template with the help of Adobe PhotoShop you will have to do next steps:

1. Launch PhotoShop application
2. Create new file 320*240 points with resolution 72 dpi
3. Copy the image and resize it to the necessary image size
4. Create new transparent Layer above the image
5. Select Pencil tool and choose the colour different from the present ones
6. Fill the region which should be transparent on your template with this contrast colour
7. Fill with the same colour also upper left pixel of this image
8. Save the image as png file
9. See that the extension of the file is written with small letters
10. Upload image to your phone with the help of Bluetooth or datacable to the PhotoFun - Templates folder on Phone memory or Data - Photofun - Templates folder.

After that you will be able to use your own template. You should just launch the application and change the current template to the newly created one, you will be able to change it by pressing Option – Change template and select your template form the list of available templates.

Sharing Templates

You will find other ready templates ready for download on our website. If you would like to share your templates to the community, please send them to us per e-Mail and we will publish them on our site. We can include your personal author information also.

How to uninstall PhotoFun v 1.2

In order to uninstall PhotoFun, please go to the Menu → System → Applications Manager, choose the PhotoFun Application from the list and uninstall it in the usual way.

PhotoFun Support

If you have any questions or concerns regarding the programm, please contact us at support@symbianguru.com. Our experienced support team is always ready to help you. We also encourage you to send us your ready templates if you want to share them, and we will publish them together with your name (if you wish) on our website.